


# Foxmail 设置说明

使用 Foxmail 收发邮件前，请首先到 Foxmail 网站下载最新版的 Foxmail 安装或升级，然后按照以下方法进行设置。


1. 单击右侧的"图标"，选择"账号管理"菜单项；



2. 点“新建”



3. 如下图所示，点“手动设置”自行填写好您的邮箱地址和密码；



The screenshot shows a dialog box titled "新建帐号" (New Account). It contains two input fields: "E-mail地址:" and "密码:". At the bottom left, there is a button labeled "手动设置" (Manual Settings) which is highlighted with a red box. To its right are buttons for "创建" (Create) and "取消" (Cancel). A help icon with the text "帮助" is located in the top right corner.



4. 如下图所示，在“邮箱账号和密码”处填写您的邮件地址和密码，在“POP3 服务器”处填写企业邮箱邮件的 POP3 服务器名称，比如：pop.mailer.com.cn，在“SMTP 服务器”处填写企业邮箱邮件的发件服务器，比如：smtp.mailer.com.cn，也可以都写 mail.mailer.com.cn；




The screenshot shows the same "新建帐号" dialog box, but now with several fields filled in. The "接收服务器类型" (Receive server type) dropdown is set to "POP3". The "邮件帐号" (Email account) field contains "jindi@mailer.com.cn". The "密码" (Password) field is filled with asterisks. The "POP 服务器" (POP server) field contains "mail.mailer.com.cn", with an unchecked "SSL" checkbox and a "端口" (Port) of "110". The "SMTP 服务器" (SMTP server) field also contains "mail.mailer.com.cn", with an unchecked "SSL" checkbox and a "端口" of "25". There is a checkbox for "如果服务器支持，就使用STARTTLS加密传输(T)" (Use STARTTLS encryption if supported by the server) which is currently unchecked. A "代理设置" (Proxy settings) button is located below the checkboxes. At the bottom, there are buttons for "返回" (Back), "创建" (Create), and "取消" (Cancel).

5. 单击"创建"按钮打开"设置成功"提示页面，如下图所示，单击"完成"按钮关闭窗口，并


回到 Foxmail 邮件夹页面，新建立的帐户将显示在 Foxmail 的主页面：



6. 选中新建立的邮箱，可以进行邮箱设置：



7. 点“服务器”进行服务器的设置



8. 全部设置完成后，点应用、确定，就可以进行收发邮件

